# Lecture 4 Blood Flow, Pressure & Resistance - 1



HN Mayrovitz PhD mayrovit@nova.edu drmayrovitz.com

### Topics

- Pressures and flow in the vascular circuit
- Vascular resistance
- Vascular patterns and arrangements
- Measuring blood pressure
- Blood pressure standards
- Measuring cardiac output
- Cardiac output distribution
- Blood pressure distribution
- Pulmonary pressures
- Interactive questions

### **Vascular Circuit with Pressures and Flows Defined**



### **Vascular Resistance Concept**



SVR = Systemic Vascular Resistance TPR = Total Peripheral Resistance △P/CO = (MAP – CVP)/CO = (93 - 3 mmHg)/(5 L/min) = 18 mmHg/L/min = 18 "Wood" units

SVR = TPR = mmHg/(L/min) = Wood Unit If mmHg/ml/min = PRU = Wood Unit/1000

"Normal" values 15-20 Wood units → 0.015-0.020 PRU



### Vasculature: Vessel Types-Structure-Components



Note that:

- Smallest diameter is the capillary that has no vascular smooth muscle (VSM)
- What is called a "precapillary sphincter" refers to a terminal arteriole that immediately precedes the capillary network – largest relative amount of VSM
- The larger arteries have relatively more elastic material (elastin > fibrous collagen)
- Wall thickness to diameter is low in veins versus arteries  $\rightarrow$  effects compliance

### Vascular Resistances: Series vs. Parallel Arrangement



Organs or Vasculatures in SERIES

- •Flow same in series-coupled parts
- Resistances sum directly
- Total R greater than individual R
- Pressure is lost sequentially



 $1/R_{T} = 1/R_{1} + 1/R_{2}$ 

Organs or Vasculatures in PARALLEL

- •Perfusion Pressures are the same
- Resistances sum reciprocally
- Total R is LESS than any individual R



- Organs are in parallel with other organs (x, y and z)
- So, flow to each organ depends on its vascular resistance since all have equal perfusion pressure Within Organs
- Arterioles are ≈ in parallel with arterioles
- Capillaries are ≈ in parallel with capillaries BUT
- Segments are in series with the other segments
- Since in series pressure is lost across each segment

### **Cardiovascular Patterns and Arrangements**



## **Measuring BP: Sphygmomanometer**



### Measuring BP: Oscillographic Method



Systolic & Diastolic via algorithm



### **Hypertension = High Blood Pressure**

## So ..... What's High?

## Hypertension

BP CLASSIFICATION	SBP (mmHg)	DBP (mmHg)
Normal	< 120	AND <80
Elevated	120-129	AND < 80
Stage 1 Hypertension	130 - 139	OR 80 - 89
Stage 2 Hypertension	>= 140	OR >= 90
Hypertensive Crisis	> 180	AND/OR > 120

If DBP is normal but SBP is high then it may be called Isolated Systolic Hypertension (e.g. 145/75, also stage 2 HTN) → Decreased Arterial Compliance

Which (is) are normotensive?

Which (is) are stage 1 hypertension?

Which (is) are isolated systolic hypertension?



### **Determining CO via Thermodilution Method**

#### Thermodilution

Swan-Ganz catheter with thermistor placed into pulmonary artery via peripheral vein insertion

 Cold saline injected into right atrium at \_
end of expiration





Dr HN Mayrovitz

### **Resting Cardiac Output Distribution**



The above figure shows approximate percentages of cardiac output distribution. If CO were 6 L/min then absolute flow to the kidneys would be 1.2 L/min.

- Percentages are approximate; vary by person
- Absolute cardiac output (CO, L/min) varies by age, gender, weight and other
- Cardiac Index (CO/BSA, L/min/m<sup>2</sup>) helps minimize variance also (SVI = SV/BSA)
- For a fixed perfusion pressure, flow (Q) distribution to organs depends on its vascular resistance;  $\mathbf{Q} = \Delta \mathbf{P}/\mathbf{R}$
- The diagram below shows pressures in mmHg and illustrates normal average values at the different locations



Perfusion pressure =  $\Delta P$  = 95-5 = 90 mmHg If cardiac output were 6 L/min then TPR = 90/6 = 15 Wood units and PVR = 10/6 = 1.67 Wood units

### **Cardiovascular Pressure Variations**



### **Vascular Pathways: Volume-Pressure-Velocity**



(A) Blood volume: Arterial 15% Venous 60% Pulmonary 25%

#### (B) Mean arterial pressure:

- 1. little change in large arteries;
- 2. large change across arterioles
- 3. low value in capillaries & veins

### (C) Cross-sectional area:

Largest in capillary network despite their small diameter due to their large numbers

### (D) Mean Blood Velocity:

- 1. Same total flow passes through each series vascular network
- 2. Network with largest cross-sectional area has the *least blood velocity*.
- 3. Least in systemic/pulmonary capillaries

Dr HN Mayrovitz









Bill has the following hemodynamic data ABP = 150/60 mmHg CVP = 3 mmHg SV = 100 ml HR = 50

What is his TPR in Wood units?



Which of the following best describes conditions within a vascular bed of an organ?

- A. All capillaries of the same type are effectively in parallel with each other
- B. All arterioles of the same type are effectively in parallel with capillaries they supply
- C. The greatest pressure loss is attributable to the small lumen of the capillaries
- D. All arterioles of the same type are effectively in series with each other
- E. A decrease in the number of arterioles leads to a decrease in organ resistance

.

If all arterioles of an organ vasoconstrict then:

- A. Blood flow to the organ increases
- **B.** Blood pressure in the organ's capillaries decreases
- C. Total resistance of the organ decreases
- D. Blood flow within arterioles increases
- E. Total peripheral resistance decreases

Which one of the following is not usually a major function or attribute of systemic arterioles?

- A. Control of the amount of blood flow that enters an organ
- **B.** Control of the amount of blood pressure in the capillaries
- C. Control of the vascular resistance of an organ
- D. Control of the systemic blood pressure
- E. Control of the systemic blood volume



Which of the following features is numerically similar in the systemic and pulmonary circulations?

- A. Systolic blood pressure
- **B.** Diastolic blood pressure
- C. Mean blood pressure
- D. Total blood flow
- E. Ventricular maximum pressure

# **End CV Physiology Lecture 4**

Dr HN Mayrovitz